



# Trimax Meters SM-4500 USB Upgrade

1. Turn your meter on and press "MENU" to show the main menu
2. Insert your USB drive with the upgrade you would like to install.
3. Choose "System Setting" and press the "OK" key.




4. Scroll down to the "Upgrade" button and press the "OK" key.



# Trimax Meters SM-4500 USB Upgrade

5. Highlight the "USB Upgrade" button and press the "OK" key.



6. Highlight the "All" button and press the "OK" key.
7. The USB drive indicator will open. Make sure it is highlighted and press "OK".
8. Choose the file you want to install from the list that is now showing.
9. Press "OK" and "Download". The file will download to the meter and the meter will reboot. The meter is now ready to use.